

Solid Edge 2024 Licence Server Set-up

This Tech Tip looks at setting up the new licence server for Solid Edge 2024.

Download

Start by going to the downloads for Solid Edge and choose [Solid Edge 2024 \(V2310\) Add-ons](#)

Select a Version

Solid Edge 2024 (v2310) ▾



Then click on SptTools on the left and download the SptTools_2024_2310.zip.

Solid Edge

Solid Edge 2024 (v2310) Add-ons More Versions

A screenshot of the Solid Edge 2024 (v2310) Add-ons download page. The page has a light blue header with the text "Solid Edge 2024 (v2310) Add-ons" and a "More Versions" button. Below the header is a search bar with "Solid Edge 2024 (v2310) Add-ons" and a dropdown menu. There is a language selector set to "English". A table lists the add-ons with columns for "OS" and "File Name". The "SptTools_2024_2310.zip" file is highlighted, showing it is for "Windows64" and has the tag "SptTools". A mouse cursor is pointing at the file name.

Unzip this file and open the LicenseServer folder.

Obtain Licence File

Before progressing further, ensure that you have a copy of your new licence file from the [licencing website](#).


Have the new licence file stored somewhere else as it will re-configure it and put in the right place and rename it.

Uninstall


Uninstall all old versions of Solid Edge licence server using Add or Remove Programs.

Run SiemensLicenseServer_v2.2.2.0_Win64_x86-64.exe


Set Language to English




Use Rename existing files




Browse for new file




Click to use Advanced Settings



Use default folder



Enter webkey email address



The screenshot shows a window titled "Siemens License Server Installer 2.2.2.0" with the Siemens logo and the heading "Enter Webkey". On the left is a blue abstract network graphic. The main text explains the Siemens License Install Manager (SLIM) and provides a link to a support center article. It prompts the user to enter a Siemens Account (Webkey), Support Center login, or email of an authorized administrator. A text box contains the email "alan@cadcentral.co.nz". A note states that the email is encrypted and stored locally. There is an unchecked checkbox for "I don't want this feature". At the bottom right are buttons for "Back", "Next", and "Cancel", with a mouse cursor pointing at "Next".

Siemens License Server Installer 2.2.2.0

SIEMENS **Enter Webkey**

The Siemens License Install Manager (SLIM) will facilitate administrative tasks such as updating license files, applying server patches, and viewing the license server status & logs.

For more information see [Support Center](#) KB Article MG621081.

Enter a Siemens Account (Webkey), Support Center login, or email of an authorized administrator for this License Server

alan@cadcentral.co.nz

Note: The email you enter in this window is encrypted and stored locally on the server and is not sent to Siemens or used for any other purpose.

I don't want this feature

Back **Next** **Cancel**

Confirm Install